

1  
2  
3  
4  
5  
6  
7  
8  
9  
10  
11  
12  
13  
14  
15  
16  
17  
18  
19  
20  
21  
22  
23  
24  
25  
26  
27  
28

IN THE UNITED STATES DISTRICT COURT  
FOR THE SOUTHERN DISTRICT OF CALIFORNIA

ADVANCED MEDIA NETWORKS,  
LLC,

Plaintiff,

v.

VIASAT, INC., ET AL,  
Defendants.

Case No.: 3:15-cv-00143-BEN-MDD

**DECLARATION OF THE RFC EDITOR  
ON BEHALF OF THE INTERNET  
ENGINEERING TASK FORCE, AN  
ORGANIZED ACTIVITY OF THE  
INTERNET SOCIETY**

---

I, Sandy Ginoza, based on my personal knowledge and information, hereby  
declare as follows:

1. I am an employee of Association Management Solutions, LLC  
(AMS), which acts under contract to the Internet Society (ISOC) as the operator of  
the RFC Production Center. The RFC Production Center is part of the "RFC  
Editor" function, which prepares documents for publication and places files in an  
online repository for the authoritative Request for Comments (RFC) series of  
documents (RFC Series), and preserves records relating to these documents. The  
RFC Series includes, among other things, the series of Internet standards  
developed by the Internet Engineering Task Force (IETF), an organized activity of  
ISOC. I hold the position of Director of the RFC Production Center. I began  
employment with AMS in this capacity on 6 January 2010.

2. Among my responsibilities as Director of the RFC Production Center,  
I act as the custodian of records relating to the RFC Series, and I am familiar with  
the record keeping practices relating to the RFC Series, including the creation and  
maintenance of such records.

1           3.     From June 1999 to 5 January 2010, I was an employee of the  
2 Information Sciences Institute at University of Southern California (ISI). I held  
3 various position titles with the RFC Editor project at ISI, ending with Senior  
4 Editor.

5           4.     The RFC Editor function was conducted by ISI under contract to the  
6 United States government prior to 1998. In 1998, ISOC, in furtherance of its  
7 IETF activity, entered into the first in a series of contracts with ISI providing for  
8 ISI's performance of the RFC Editor function. Beginning in 2010, certain aspects  
9 of the RFC Editor function were assumed by the RFC Production Center operation  
10 of AMS under contract to ISOC (acting through its IETF function and, in  
11 particular, the IETF Administrative Oversight Committee). The business records  
12 of the RFC Editor function as it was conducted by ISI are currently housed on the  
13 computer systems of AMS, as contractor to ISOC.

14           5.     I make this declaration based on my personal knowledge and  
15 information contained in the business records of the RFC Editor as they are  
16 currently housed at AMS, or confirmation with other responsible RFC Editor  
17 personnel with such knowledge.

18           6.     Prior to 1998, the RFC Editor's regular practice was to publish RFCs,  
19 making them available from a repository via FTP. When a new RFC was  
20 published, an announcement of its publication, with information on how to access  
21 the RFC, would be typically sent out within 24 hours of the publication. A  
22 contemporaneous electronic record of the announcement was made and kept in the  
23 IETF mail archive.

24           7.     Any RFC published via FTP was reasonably accessible to the public  
25 and was disseminated or otherwise available to the extent that persons interested  
26 and ordinarily skilled in the subject matter or art exercising reasonable diligence  
27  
28

1 could have located it. In particular, the RFCs were indexed and placed in a public  
2 repository.

3 8. The RFCs are kept in an online repository in the course of the RFC  
4 Editor's regularly conducted activity and ordinary course of business. The records  
5 are made pursuant to established procedures and are relied upon by the RFC  
6 Editor in the performance of its functions.

7 9. It is the regular practice of the RFC Editor to make and keep the RFC  
8 records.

9 10. Exhibit VIASAT 1008 attached hereto is a true and correct copy of  
10 RFC 1459.

11 11. Based on my review of the RFC Editor's business records, I have  
12 determined that RFC 1459 was published on or about May 1993 via FTP.  
13

14 Pursuant to Section 1746 of Title 28 of United States Code, I declare under  
15 penalty of perjury under the laws of the United States of America that the  
16 foregoing is true and correct and that the foregoing is based upon personal  
17 knowledge and information and is believed to be true.  
18

19 Date: 16 February 2016

20 By: \_\_\_\_\_

21   
Sandy Ginoza  
22  
23  
24  
25  
26  
27  
28

## Internet Relay Chat Protocol

### Status of This Memo

This memo defines an Experimental Protocol for the Internet community. Discussion and suggestions for improvement are requested. Please refer to the current edition of the "IAB Official Protocol Standards" for the standardization state and status of this protocol. Distribution of this memo is unlimited.

### Abstract

The IRC protocol was developed over the last 4 years since it was first implemented as a means for users on a BBS to chat amongst themselves. Now it supports a world-wide network of servers and clients, and is stringing to cope with growth. Over the past 2 years, the average number of users connected to the main IRC network has grown by a factor of 10.

The IRC protocol is a text-based protocol, with the simplest client being any socket program capable of connecting to the server.

### Table of Contents

1. INTRODUCTION .....	4
1.1 Servers .....	4
1.2 Clients .....	5
1.2.1 Operators .....	5
1.3 Channels .....	5
1.3.1 Channel Operators .....	6
2. THE IRC SPECIFICATION .....	7
2.1 Overview .....	7
2.2 Character codes .....	7
2.3 Messages .....	7
2.3.1 Message format in 'pseudo' BNF .....	8
2.4 Numeric replies .....	10
3. IRC Concepts .....	10
3.1 One-to-one communication .....	10
3.2 One-to-many .....	11
3.2.1 To a list .....	11
3.2.2 To a group (channel) .....	11
3.2.3 To a host/server mask .....	12
3.3 One to all .....	12

3.3.1 Client to Client .....	12
3.3.2 Clients to Server .....	12
3.3.3 Server to Server .....	12
4. MESSAGE DETAILS .....	13
4.1 Connection Registration .....	13
4.1.1 Password message .....	14
4.1.2 Nickname message .....	14
4.1.3 User message .....	15
4.1.4 Server message .....	16
4.1.5 Operator message .....	17
4.1.6 Quit message .....	17
4.1.7 Server Quit message .....	18
4.2 Channel operations .....	19
4.2.1 Join message .....	19
4.2.2 Part message .....	20
4.2.3 Mode message .....	21
4.2.3.1 Channel modes .....	21
4.2.3.2 User modes .....	22
4.2.4 Topic message .....	23
4.2.5 Names message .....	24
4.2.6 List message .....	24
4.2.7 Invite message .....	25
4.2.8 Kick message .....	25
4.3 Server queries and commands .....	26
4.3.1 Version message .....	26
4.3.2 Stats message .....	27
4.3.3 Links message .....	28
4.3.4 Time message .....	29
4.3.5 Connect message .....	29
4.3.6 Trace message .....	30
4.3.7 Admin message .....	31
4.3.8 Info message .....	31
4.4 Sending messages .....	32
4.4.1 Private messages .....	32
4.4.2 Notice messages .....	33
4.5 User-based queries .....	33
4.5.1 Who query .....	33
4.5.2 Whois query .....	34
4.5.3 Whowas message .....	35
4.6 Miscellaneous messages .....	35
4.6.1 Kill message .....	36
4.6.2 Ping message .....	37
4.6.3 Pong message .....	37
4.6.4 Error message .....	38
5. OPTIONAL MESSAGES .....	38
5.1 Away message .....	38
5.2 Rehash command .....	39
5.3 Restart command .....	39

5.4	Summon message .....	40
5.5	Users message .....	40
5.6	Operwall command .....	41
5.7	Userhost message .....	42
5.8	Ison message .....	42
6.	REPLIES .....	43
6.1	Error Replies .....	43
6.2	Command responses .....	48
6.3	Reserved numerics .....	56
7.	Client and server authentication .....	56
8.	Current Implementations Details .....	56
8.1	Network protocol: TCP .....	57
8.1.1	Support of Unix sockets .....	57
8.2	Command Parsing .....	57
8.3	Message delivery .....	57
8.4	Connection 'Liveness' .....	58
8.5	Establishing a server-client connection .....	58
8.6	Establishing a server-server connection .....	58
8.6.1	State information exchange when connecting .....	59
8.7	Terminating server-client connections .....	59
8.8	Terminating server-server connections .....	59
8.9	Tracking nickname changes .....	60
8.10	Flood control of clients .....	60
8.11	Non-blocking lookups .....	61
8.11.1	Hostname (DNS) lookups .....	61
8.11.2	Username (Ident) lookups .....	61
8.12	Configuration file .....	61
8.12.1	Allowing clients to connect .....	62
8.12.2	Operators .....	62
8.12.3	Allowing servers to connect .....	62
8.12.4	Administrivia .....	63
8.13	Channel membership .....	63
9.	Current problems .....	63
9.1	Scalability .....	63
9.2	Labels .....	63
9.2.1	Nicknames .....	63
9.2.2	Channels .....	64
9.2.3	Servers .....	64
9.3	Algorithms .....	64
10.	Support and availability .....	64
11.	Security Considerations .....	65
12.	Authors' Addresses .....	65

## 1. INTRODUCTION


The IRC (Internet Relay Chat) protocol has been designed over a number of years for use with text based conferencing. This document describes the current IRC protocol.

The IRC protocol has been developed on systems using the TCP/IP network protocol, although there is no requirement that this remain the only sphere in which it operates.

IRC itself is a teleconferencing system, which (through the use of the client-server model) is well-suited to running on many machines in a distributed fashion. A typical setup involves a single process (the server) forming a central point for clients (or other servers) to connect to, performing the required message delivery/multiplexing and other functions.

## 1.1 Servers

The server forms the backbone of IRC, providing a point to which clients may connect to to talk to each other, and a point for other servers to connect to, forming an IRC network. The only network configuration allowed for IRC servers is that of a spanning tree [see Fig. 1] where each server acts as a central node for the rest of the net it sees.



[ Fig. 1. Format of IRC server network ]

## 1.2 Clients

A client is anything connecting to a server that is not another server. Each client is distinguished from other clients by a unique nickname having a maximum length of nine (9) characters. See the protocol grammar rules for what may and may not be used in a nickname. In addition to the nickname, all servers must have the following information about all clients: the real name of the host that the client is running on, the username of the client on that host, and the server to which the client is connected.

### 1.2.1 Operators

To allow a reasonable amount of order to be kept within the IRC network, a special class of clients (operators) is allowed to perform general maintenance functions on the network. Although the powers granted to an operator can be considered as 'dangerous', they are nonetheless required. Operators should be able to perform basic network tasks such as disconnecting and reconnecting servers as needed to prevent long-term use of bad network routing. In recognition of this need, the protocol discussed herein provides for operators only to be able to perform such functions. See sections 4.1.7 (SQUIT) and 4.3.5 (CONNECT).

A more controversial power of operators is the ability to remove a user from the connected network by 'force', i.e. operators are able to close the connection between any client and server. The justification for this is delicate since its abuse is both destructive and annoying. For further details on this type of action, see section 4.6.1 (KILL).

## 1.3 Channels

A channel is a named group of one or more clients which will all receive messages addressed to that channel. The channel is created implicitly when the first client joins it, and the channel ceases to exist when the last client leaves it. While channel exists, any client can reference the channel using the name of the channel.

Channels names are strings (beginning with a '&' or '#' character) of length up to 200 characters. Apart from the the requirement that the first character being either '&' or '#'; the only restriction on a channel name is that it may not contain any spaces (' '), a control G (^G or ASCII 7), or a comma (',') which is used as a list item separator by the protocol).

There are two types of channels allowed by this protocol. One is a distributed channel which is known to all the servers that are



connected to the network. These channels are marked by the first character being a only clients on the server where it exists may join it. These are distinguished by a leading '&' character. On top of these two types, there are the various channel modes available to alter the characteristics of individual channels. See section 4.2.3 (MODE command) for more details on this.

To create a new channel or become part of an existing channel, a user is required to JOIN the channel. If the channel doesn't exist prior to joining, the channel is created and the creating user becomes a channel operator. If the channel already exists, whether or not your request to JOIN that channel is honoured depends on the current modes of the channel. For example, if the channel is invite-only, (+i), then you may only join if invited. As part of the protocol, a user may be a part of several channels at once, but a limit of ten (10) channels is recommended as being ample for both experienced and novice users. See section 8.13 for more information on this.

If the IRC network becomes disjoint because of a split between two servers, the channel on each side is only composed of those clients which are connected to servers on the respective sides of the split, possibly ceasing to exist on one side of the split. When the split is healed, the connecting servers announce to each other who they think is in each channel and the mode of that channel. If the channel exists on both sides, the JOINS and MODEs are interpreted in an inclusive manner so that both sides of the new connection will agree about which clients are in the channel and what modes the channel has.

#### 1.3.1 Channel Operators

The channel operator (also referred to as a "chop" or "chanop") on a given channel is considered to 'own' that channel. In recognition of this status, channel operators are endowed with certain powers which enable them to keep control and some sort of sanity in their channel. As an owner of a channel, a channel operator is not required to have reasons for their actions, although if their actions are generally antisocial or otherwise abusive, it might be reasonable to ask an IRC operator to intervene, or for the users just leave and go elsewhere and form their own channel.

The commands which may only be used by channel operators are:

KICK	- Eject a client from the channel
MODE	- Change the channel's mode
INVITE	- Invite a client to an invite-only channel (mode +i)
TOPIC	- Change the channel topic in a mode +t channel

A channel operator is identified by the '@' symbol next to their nickname whenever it is associated with a channel (ie replies to the NAMES, WHO and WHOIS commands).

## 2. The IRC Specification

### 2.1 Overview

The protocol as described herein is for use both with server to server and client to server connections. There are, however, more restrictions on client connections (which are considered to be untrustworthy) than on server connections.

### 2.2 Character codes

No specific character set is specified. The protocol is based on a set of codes which are composed of eight (8) bits, making up an octet. Each message may be composed of any number of these octets; however, some octet values are used for control codes which act as message delimiters.

Regardless of being an 8-bit protocol, the delimiters and keywords are such that protocol is mostly usable from USASCII terminal and a telnet connection.

Because of IRC's scandinavian origin, the characters {}| are considered to be the lower case equivalents of the characters []\, respectively. This is a critical issue when determining the equivalence of two nicknames.

### 2.3 Messages

Servers and clients send eachother messages which may or may not generate a reply. If the message contains a valid command, as described in later sections, the client should expect a reply as specified but it is not advised to wait forever for the reply; client to server and server to server communication is essentially asynchronous in nature.

Each IRC message may consist of up to three main parts: the prefix (optional), the command, and the command parameters (of which there may be up to 15). The prefix, command, and all parameters are separated by one (or more) ASCII space character(s) (0x20).

The presence of a prefix is indicated with a single leading ASCII colon character (':', 0x3b), which must be the first character of the message itself. There must be no gap (whitespace) between the colon and the prefix. The prefix is used by servers to indicate the true

origin of the message. If the prefix is missing from the message, it is assumed to have originated from the connection from which it was received. Clients should not use prefix when sending a message from themselves; if they use a prefix, the only valid prefix is the registered nickname associated with the client. If the source identified by the prefix cannot be found from the server's internal database, or if the source is registered from a different link than from which the message arrived, the server must ignore the message silently.

The command must either be a valid IRC command or a three (3) digit number represented in ASCII text.

IRC messages are always lines of characters terminated with a CR-LF (Carriage Return - Line Feed) pair, and these messages shall not exceed 512 characters in length, counting all characters including the trailing CR-LF. Thus, there are 510 characters maximum allowed for the command and its parameters. There is no provision for continuation message lines. See section 7 for more details about current implementations.

### 2.3.1 Message format in 'pseudo' BNF

The protocol messages must be extracted from the contiguous stream of octets. The current solution is to designate two characters, CR and LF, as message separators. Empty messages are silently ignored, which permits use of the sequence CR-LF between messages without extra problems.

The extracted message is parsed into the components <prefix>, <command> and list of parameters matched either by <middle> or <trailing> components.

The BNF representation for this is:

```

<message> ::= [ ':' <prefix> <SPACE> ] <command> <params> <crlf>
<prefix>  ::= <servername> | <nick> [ '!' <user> ] [ '@' <host> ]
<command> ::= <letter> { <letter> } | <number> <number> <number>
<SPACE>   ::= ' ' { ' ' }
<params>   ::= <SPACE> [ ':' <trailing> | <middle> <params> ]

<middle>   ::= <Any *non-empty* sequence of octets not including SPACE
               or NUL or CR or LF, the first of which may not be ':'>
<trailing> ::= <Any, possibly *empty*, sequence of octets not including
               NUL or CR or LF>

<crlf>     ::= CR LF

```

## NOTES:

- 1) <SPACE> is consists only of SPACE character(s) (0x20). Specially notice that TABULATION, and all other control characters are considered NON-WHITE-SPACE.
- 2) After extracting the parameter list, all parameters are equal, whether matched by <middle> or <trailing>. <Trailing> is just a syntactic trick to allow SPACE within parameter.
- 3) The fact that CR and LF cannot appear in parameter strings is just artifact of the message framing. This might change later.
- 4) The NUL character is not special in message framing, and basically could end up inside a parameter, but as it would cause extra complexities in normal C string handling. Therefore NUL is not allowed within messages.
- 5) The last parameter may be an empty string.
- 6) Use of the extended prefix ([ '!' <user> ] [ '@' <host> ]) must not be used in server to server communications and is only intended for server to client messages in order to provide clients with more useful information about who a message is from without the need for additional queries.

Most protocol messages specify additional semantics and syntax for the extracted parameter strings dictated by their position in the list. For example, many server commands will assume that the first parameter after the command is the list of targets, which can be described with:

```

<target>      ::= <to> [ ", " <target> ]
<to>          ::= <channel> | <user> '@' <servername> | <nick> | <mask>
<channel>     ::= ('#' | '&') <chstring>
<servername> ::= <host>
<host>        ::= see RFC 952 [DNS:4] for details on allowed hostnames
<nick>        ::= <letter> { <letter> | <number> | <special> }
<mask>        ::= ('#' | '$') <chstring>
<chstring>    ::= <any 8bit code except SPACE, BELL, NUL, CR, LF and
                  comma (',')>

```

Other parameter syntaxes are:

```

<user>        ::= <nonwhite> { <nonwhite> }
<letter>      ::= 'a' ... 'z' | 'A' ... 'Z'
<number>      ::= '0' ... '9'
<special>     ::= '-' | '[' | ']' | '\' | ''' | '^' | '{' | '}'

```


```
<nonwhite> ::= <any 8bit code except SPACE (0x20), NUL (0x0), CR
              (0xd), and LF (0xa)>
```

## 2.4 Numeric replies

Most of the messages sent to the server generate a reply of some sort. The most common reply is the numeric reply, used for both errors and normal replies. The numeric reply must be sent as one message consisting of the sender prefix, the three digit numeric, and the target of the reply. A numeric reply is not allowed to originate from a client; any such messages received by a server are silently dropped. In all other respects, a numeric reply is just like a normal message, except that the keyword is made up of 3 numeric digits rather than a string of letters. A list of different replies is supplied in section 6.

## 3. IRC Concepts.

This section is devoted to describing the actual concepts behind the organization of the IRC protocol and how the current implementations deliver different classes of messages.



Servers: A, B, C, D, E

Clients: 1, 2, 3, 4

[ Fig. 2. Sample small IRC network ]

### 3.1 One-to-one communication

Communication on a one-to-one basis is usually only performed by clients, since most server-server traffic is not a result of servers talking only to each other. To provide a secure means for clients to talk to each other, it is required that all servers be able to send a message in exactly one direction along the spanning tree in order to reach any client. The path of a message being delivered is the shortest path between any two points on the spanning tree.

The following examples all refer to Figure 2 above.

**Example 1:**

A message between clients 1 and 2 is only seen by server A, which sends it straight to client 2.

**Example 2:**

A message between clients 1 and 3 is seen by servers A & B, and client 3. No other clients or servers are allowed see the message.

**Example 3:**

A message between clients 2 and 4 is seen by servers A, B, C & D and client 4 only.

### 3.2 One-to-many

The main goal of IRC is to provide a forum which allows easy and efficient conferencing (one to many conversations). IRC offers several means to achieve this, each serving its own purpose.

#### 3.2.1 To a list

The least efficient style of one-to-many conversation is through clients talking to a 'list' of users. How this is done is almost self explanatory: the client gives a list of destinations to which the message is to be delivered and the server breaks it up and dispatches a separate copy of the message to each given destination. This isn't as efficient as using a group since the destination list is broken up and the dispatch sent without checking to make sure duplicates aren't sent down each path.

#### 3.2.2 To a group (channel)

In IRC the channel has a role equivalent to that of the multicast group; their existence is dynamic (coming and going as people join and leave channels) and the actual conversation carried out on a channel is only sent to servers which are supporting users on a given channel. If there are multiple users on a server in the same channel, the message text is sent only once to that server and then sent to each client on the channel. This action is then repeated for each client-server combination until the original message has fanned out and reached each member of the channel.

The following examples all refer to Figure 2.

**Example 4:**

Any channel with 1 client in it. Messages to the channel go to the server and then nowhere else.

**Example 5:**

2 clients in a channel. All messages traverse a path as if they were private messages between the two clients outside a channel.

**Example 6:**

Clients 1, 2 and 3 in a channel. All messages to the channel are sent to all clients and only those servers which must be traversed by the message if it were a private message to a single client. If client 1 sends a message, it goes back to client 2 and then via server B to client 3.

**3.2.3 To a host/server mask**

To provide IRC operators with some mechanism to send messages to a large body of related users, host and server mask messages are provided. These messages are sent to users whose host or server information match that of the mask. The messages are only sent to locations where users are, in a fashion similar to that of channels.

**3.3 One-to-all**

The one-to-all type of message is better described as a broadcast message, sent to all clients or servers or both. On a large network of users and servers, a single message can result in a lot of traffic being sent over the network in an effort to reach all of the desired destinations.

For some messages, there is no option but to broadcast it to all servers so that the state information held by each server is reasonably consistent between servers.

**3.3.1 Client-to-Client**

There is no class of message which, from a single message, results in a message being sent to every other client.

**3.3.2 Client-to-Server**

Most of the commands which result in a change of state information (such as channel membership, channel mode, user status, etc) must be sent to all servers by default, and this distribution may not be changed by the client.

**3.3.3 Server-to-Server.**

While most messages between servers are distributed to all 'other' servers, this is only required for any message that affects either a user, channel or server. Since these are the basic items found in

IRC, nearly all messages originating from a server are broadcast to all other connected servers.

#### 4. Message details

On the following pages are descriptions of each message recognized by the IRC server and client. All commands described in this section must be implemented by any server for this protocol.

Where the reply ERR\_NOSUCHSERVER is listed, it means that the <server> parameter could not be found. The server must not send any other replies after this for that command.

The server to which a client is connected is required to parse the complete message, returning any appropriate errors. If the server encounters a fatal error while parsing a message, an error must be sent back to the client and the parsing terminated. A fatal error may be considered to be incorrect command, a destination which is otherwise unknown to the server (server, nick or channel names fit this category), not enough parameters or incorrect privileges.

If a full set of parameters is presented, then each must be checked for validity and appropriate responses sent back to the client. In the case of messages which use parameter lists using the comma as an item separator, a reply must be sent for each item.

In the examples below, some messages appear using the full format:

:Name COMMAND parameter list

Such examples represent a message from "Name" in transit between servers, where it is essential to include the name of the original sender of the message so remote servers may send back a reply along the correct path.

##### 4.1 Connection Registration

The commands described here are used to register a connection with an IRC server as either a user or a server as well as correctly disconnect.

A "PASS" command is not required for either client or server connection to be registered, but it must precede the server message or the latter of the NICK/USER combination. It is strongly recommended that all server connections have a password in order to give some level of security to the actual connections. The recommended order for a client to register is as follows:



1. Pass message
2. Nick message
3. User message

#### 4.1.1 Password message

Command: PASS

Parameters: <password>

The PASS command is used to set a 'connection password'. The password can and must be set before any attempt to register the connection is made. Currently this requires that clients send a PASS command before sending the NICK/USER combination and servers *\*must\** send a PASS command before any SERVER command. The password supplied must match the one contained in the C/N lines (for servers) or I lines (for clients). It is possible to send multiple PASS commands before registering but only the last one sent is used for verification and it may not be changed once registered. Numeric Replies:

ERR\_NEEDMOREPARAMS

ERR\_ALREADYREGISTERED

Example:

PASS secretpasswordhere

#### 4.1.2 Nick message

Command: NICK

Parameters: <nickname> [ <hopcount> ]

NICK message is used to give user a nickname or change the previous one. The <hopcount> parameter is only used by servers to indicate how far away a nick is from its home server. A local connection has a hopcount of 0. If supplied by a client, it must be ignored.

If a NICK message arrives at a server which already knows about an identical nickname for another client, a nickname collision occurs. As a result of a nickname collision, all instances of the nickname are removed from the server's database, and a KILL command is issued to remove the nickname from all other server's database. If the NICK message causing the collision was a nickname change, then the original (old) nick must be removed as well.

If the server receives an identical NICK from a client which is directly connected, it may issue an ERR\_NICKCOLLISION to the local client, drop the NICK command, and not generate any kills.

## Numeric Replies:

ERR\_NONICKNAMEGIVEN  
ERR\_NICKNAMEINUSE

ERR\_ERRONEUSNICKNAME  
ERR\_NICKCOLLISION

## Example:

NICK Wiz ; Introducing new nick "Wiz".  
:WiZ NICK Kilroy ; WiZ changed his nickname to Kilroy.

## 4.1.3 User message

Command: USER

Parameters: &lt;username&gt; &lt;hostname&gt; &lt;servername&gt; &lt;realname&gt;

The USER message is used at the beginning of connection to specify the username, hostname, servername and realname of a new user. It is also used in communication between servers to indicate new user arriving on IRC, since only after both USER and NICK have been received from a client does a user become registered.

Between servers USER must to be prefixed with client's NICKname. Note that hostname and servername are normally ignored by the IRC server when the USER command comes from a directly connected client (for security reasons), but they are used in server to server communication. This means that a NICK must always be sent to a remote server when a new user is being introduced to the rest of the network before the accompanying USER is sent.

It must be noted that realname parameter must be the last parameter, because it may contain space characters and must be prefixed with a colon (':') to make sure this is recognised as such.

Since it is easy for a client to lie about its username by relying solely on the USER message, the use of an "Identity Server" is recommended. If the host which a user connects from has such a server enabled the username is set to that as in the reply from the "Identity Server".

## Numeric Replies:

ERR\_NEEDMOREPARAMS

ERR\_ALREADYREGISTERED

## Examples:

USER guest tolmoon tolsun :Ronnie Reagan

```
; User registering themselves with a
username of "guest" and real name
"Ronnie Reagan".
```

```
:testnick USER guest tolmoon tolsun :Ronnie Reagan
; message between servers with the
nickname for which the USER command
belongs to
```

#### 4.1.4 Server message

Command: SERVER  
Parameters: <servername> <hopcount> <info>

The server message is used to tell a server that the other end of a new connection is a server. This message is also used to pass server data over whole net. When a new server is connected to net, information about it be broadcast to the whole network. <hopcount> is used to give all servers some internal information on how far away all servers are. With a full server list, it would be possible to construct a map of the entire server tree, but hostmasks prevent this from being done.

The SERVER message must only be accepted from either (a) a connection which is yet to be registered and is attempting to register as a server, or (b) an existing connection to another server, in which case the SERVER message is introducing a new server behind that server.

Most errors that occur with the receipt of a SERVER command result in the connection being terminated by the destination host (target SERVER). Error replies are usually sent using the "ERROR" command rather than the numeric since the ERROR command has several useful properties which make it useful here.

If a SERVER message is parsed and attempts to introduce a server which is already known to the receiving server, the connection from which that message must be closed (following the correct procedures), since a duplicate route to a server has formed and the acyclic nature of the IRC tree broken.

Numeric Replies:

ERR\_ALREADYREGISTRED

Example:

```
SERVER test.oulu.fi 1 :[tolsun.oulu.fi] Experimental server
                        ; New server test.oulu.fi introducing
                        itself and attempting to register. The
                        name in []'s is the hostname for the
                        host running test.oulu.fi.
```

```
:tolsun.oulu.fi SERVER csd.bu.edu 5 :BU Central Server
                        ; Server tolsun.oulu.fi is our uplink
                        for csd.bu.edu which is 5 hops away.
```

#### 4.1.5 Oper

Command: OPER  
Parameters: <user> <password>

OPER message is used by a normal user to obtain operator privileges. The combination of <user> and <password> are required to gain Operator privileges.

If the client sending the OPER command supplies the correct password for the given user, the server then informs the rest of the network of the new operator by issuing a "MODE +o" for the clients nickname.

The OPER message is client-server only.

Numeric Replies:

ERR\_NEEDMOREPARAMS  
ERR\_NOOPERHOST

RPL\_YOUREOPER  
ERR\_PASSWDMISMATCH

Example:

```
OPER foo bar                ; Attempt to register as an operator
                             using a username of "foo" and "bar" as
                             the password.
```

#### 4.1.6 Quit

Command: QUIT  
Parameters: [<Quit message>]

A client session is ended with a quit message. The server must close the connection to a client which sends a QUIT message. If a "Quit Message" is given, this will be sent instead of the default message, the nickname.

When netsplits (disconnecting of two servers) occur, the quit message

is composed of the names of two servers involved, separated by a space. The first name is that of the server which is still connected and the second name is that of the server that has become disconnected.

If, for some other reason, a client connection is closed without the client issuing a QUIT command (e.g. client dies and EOF occurs on socket), the server is required to fill in the quit message with some sort of message reflecting the nature of the event which caused it to happen.

Numeric Replies:

None.

Examples:

QUIT :Gone to have lunch ; Preferred message format.

#### 4.1.7 Server quit message

Command: SQUIT

Parameters: <server> <comment>

The SQUIT message is needed to tell about quitting or dead servers. If a server wishes to break the connection to another server it must send a SQUIT message to the other server, using the the name of the other server as the server parameter, which then closes its connection to the quitting server.

This command is also available operators to help keep a network of IRC servers connected in an orderly fashion. Operators may also issue an SQUIT message for a remote server connection. In this case, the SQUIT must be parsed by each server inbetween the operator and the remote server, updating the view of the network held by each server as explained below.

The <comment> should be supplied by all operators who execute a SQUIT for a remote server (that is not connected to the server they are currently on) so that other operators are aware for the reason of this action. The <comment> is also filled in by servers which may place an error or similar message here.

Both of the servers which are on either side of the connection being closed are required to to send out a SQUIT message (to all its other server connections) for all other servers which are considered to be behind that link.

Similarly, a QUIT message must be sent to the other connected servers rest of the network on behalf of all clients behind that link. In addition to this, all channel members of a channel which lost a member due to the split must be sent a QUIT message.

If a server connection is terminated prematurely (e.g. the server on the other end of the link died), the server which detects this disconnection is required to inform the rest of the network that the connection has closed and fill in the comment field with something appropriate.

Numeric replies:

ERR\_NOPRIVILEGES

ERR\_NOSUCHSERVER

Example:

SQUIT tolsun.oulu.fi :Bad Link ? ; the server link tolsun.oulu.fi has been terminated because of "Bad Link".

:Trillian SQUIT cm22.eng.umd.edu :Server out of control  
; message from Trillian to disconnect  
"cm22.eng.umd.edu" from the net  
because "Server out of control".

## 4.2 Channel operations

This group of messages is concerned with manipulating channels, their properties (channel modes), and their contents (typically clients). In implementing these, a number of race conditions are inevitable when clients at opposing ends of a network send commands which will ultimately clash. It is also required that servers keep a nickname history to ensure that wherever a <nick> parameter is given, the server check its history in case it has recently been changed.

### 4.2.1 Join message

Command: JOIN

Parameters: <channel>{,<channel>} [<key>{,<key>}]

The JOIN command is used by client to start listening a specific channel. Whether or not a client is allowed to join a channel is checked only by the server the client is connected to; all other servers automatically add the user to the channel when it is received from other servers. The conditions which affect this are as follows:

1. the user must be invited if the channel is invite-only;

2. the user's nick/username/hostname must not match any active bans;
3. the correct key (password) must be given if it is set.

These are discussed in more detail under the MODE command (see section 4.2.3 for more details).

Once a user has joined a channel, they receive notice about all commands their server receives which affect the channel. This includes MODE, KICK, PART, QUIT and of course PRIVMSG/NOTICE. The JOIN command needs to be broadcast to all servers so that each server knows where to find the users who are on the channel. This allows optimal delivery of PRIVMSG/NOTICE messages to the channel.

If a JOIN is successful, the user is then sent the channel's topic (using RPL\_TOPIC) and the list of users who are on the channel (using RPL\_NAMREPLY), which must include the user joining.

Numeric Replies:

ERR_NEEDMOREPARAMS	ERR_BANNEDFROMCHAN
ERR_INVITEONLYCHAN	ERR_BADCHANNELKEY
ERR_CHANNELISFULL	ERR_BADCHANMASK
ERR_NOSUCHCHANNEL	ERR_TOOMANYCHANNELS
RPL_TOPIC	

Examples:

```
JOIN #foobar                ; join channel #foobar.
JOIN &foo fubar             ; join channel &foo using key "fubar".
JOIN #foo,&bar fubar         ; join channel #foo using key "fubar"
                           and &bar using no key.
JOIN #foo,#bar fubar,foobar ; join channel #foo using key "fubar".
                           and channel #bar using key "foobar".
JOIN #foo,#bar              ; join channels #foo and #bar.
:WiZ JOIN #Twilight_zone    ; JOIN message from WiZ
```

#### 4.2.2 Part message

Command: PART  
Parameters: <channel>{,<channel>}

The PART message causes the client sending the message to be removed from the list of active users for all given channels listed in the parameter string.

Numeric Replies:

ERR\_NEEDMOREPARAMS  
ERR\_NOTONCHANNEL

ERR\_NOSUCHCHANNEL

Examples:

```
PART #twilight_zone          ; leave channel "#twilight_zone"

PART #oz-ops,&group5          ; leave both channels "&group5" and
                              "#oz-ops".
```

#### 4.2.3 Mode message

Command: MODE

The MODE command is a dual-purpose command in IRC. It allows both usernames and channels to have their mode changed. The rationale for this choice is that one day nicknames will be obsolete and the equivalent property will be the channel.

When parsing MODE messages, it is recommended that the entire message be parsed first and then the changes which resulted then passed on.

##### 4.2.3.1 Channel modes

Parameters: <channel> {[+|-]|o|p|s|i|t|n|b|v} [<limit>] [<user>]  
[<ban mask>]

The MODE command is provided so that channel operators may change the characteristics of 'their' channel. It is also required that servers be able to change channel modes so that channel operators may be created.

The various modes available for channels are as follows:

- o - give/take channel operator privileges;
- p - private channel flag;
- s - secret channel flag;
- i - invite-only channel flag;
- t - topic settable by channel operator only flag;
- n - no messages to channel from clients on the outside;
- m - moderated channel;
- l - set the user limit to channel;



b - set a ban mask to keep users out;  
 v - give/take the ability to speak on a moderated channel;  
 k - set a channel key (password).

When using the 'o' and 'b' options, a restriction on a total of three per mode command has been imposed. That is, any combination of 'o' and

#### 4.2.3.2 User modes

Parameters: <nickname> {[+|-]|i|w|s|o}

The user MODEs are typically changes which affect either how the client is seen by others or what 'extra' messages the client is sent. A user MODE command may only be accepted if both the sender of the message and the nickname given as a parameter are both the same.

The available modes are as follows:

i - marks a users as invisible;  
 s - marks a user for receipt of server notices;  
 w - user receives wallops;  
 o - operator flag.

Additional modes may be available later on.

If a user attempts to make themselves an operator using the "+o" flag, the attempt should be ignored. There is no restriction, however, on anyone 'deopping' themselves (using "-o"). Numeric Replies:

ERR_NEEDMOREPARAMS	RPL_CHANNELMODEIS
ERR_CHANOPRIVSNEEDED	ERR_NOSUCHNICK
ERR_NOTONCHANNEL	ERR_KEYSET
RPL_BANLIST	RPL_ENDOFBANLIST
ERR_UNKNOWNMODE	ERR_NOSUCHCHANNEL
ERR_USERSDONTMATCH	RPL_UMODEIS
ERR_UMODEUNKNOWNFLAG	

Examples:

Use of Channel Modes:

MODE #Finnish +im ; Makes #Finnish channel moderated and 'invite-only'.

MODE #Finnish +o Kilroy ; Gives 'chanop' privileges to Kilroy on

```

                                channel #Finnish.

MODE #Finnish +v Wiz           ; Allow WiZ to speak on #Finnish.

MODE #Fins -s                  ; Removes 'secret' flag from channel
                                #Fins.

MODE #42 +k oulu              ; Set the channel key to "oulu".

MODE #eu-ops +l 10             ; Set the limit for the number of users
                                on channel to 10.

MODE &oulu +b                  ; list ban masks set for channel.

MODE &oulu +b *!*@*            ; prevent all users from joining.

MODE &oulu +b *!*@*.edu        ; prevent any user from a hostname
                                matching *.edu from joining.

```

#### Use of user Modes:

```

:MODE WiZ -w                   ; turns reception of WALLOPS messages
                                off for WiZ.

:Angel MODE Angel +i           ; Message from Angel to make themselves
                                invisible.

MODE WiZ -o                     ; WiZ 'deopping' (removing operator
                                status). The plain reverse of this
                                command ("MODE WiZ +o") must not be
                                allowed from users since would bypass
                                the OPER command.

```

#### 4.2.4 Topic message

Command: TOPIC  
Parameters: <channel> [<topic>]

The TOPIC message is used to change or view the topic of a channel. The topic for channel <channel> is returned if there is no <topic> given. If the <topic> parameter is present, the topic for that channel will be changed, if the channel modes permit this action.

#### Numeric Replies:

ERR_NEEDMOREPARAMS	ERR_NOTONCHANNEL
RPL_NOTOPIC	RPL_TOPIC
ERR_CHANOPRIVSNEEDED	

**Examples:**

```
:Wiz TOPIC #test :New topic      ;User Wiz setting the topic.  
TOPIC #test :another topic      ;set the topic on #test to "another  
                                topic".  
TOPIC #test                      ; check the topic for #test.
```

**4.2.5 Names message**

Command: NAMES

Parameters: [<channel>{,<channel>}]

By using the NAMES command, a user can list all nicknames that are visible to them on any channel that they can see. Channel names which they can see are those which aren't private (+p) or secret (+s) or those which they are actually on. The <channel> parameter specifies which channel(s) to return information about if valid. There is no error reply for bad channel names.

If no <channel> parameter is given, a list of all channels and their occupants is returned. At the end of this list, a list of users who are visible but either not on any channel or not on a visible channel are listed as being on 'channel' "\*".

**Numerics:**

RPL\_NAMREPLY

RPL\_ENDOFNAMES

**Examples:**

```
NAMES #twilight_zone,#42      ; list visible users on #twilight_zone  
                                and #42 if the channels are visible to  
                                you.  
NAMES                        ; list all visible channels and users
```

**4.2.6 List message**

Command: LIST

Parameters: [<channel>{,<channel>} [<server>]]

The list message is used to list channels and their topics. If the <channel> parameter is used, only the status of that channel is displayed. Private channels are listed (without their topics) as channel "Prv" unless the client generating the query is actually on that channel. Likewise, secret channels are not listed

at all unless the client is a member of the channel in question.

Numeric Replies:

ERR_NOSUCHSERVER	RPL_LISTSTART
RPL_LIST	RPL_LISTEND

Examples:

LIST ; List all channels.

LIST #twilight\_zone,#42 ; List channels #twilight\_zone and #42

#### 4.2.7 Invite message

Command: INVITE

Parameters: <nickname> <channel>

The INVITE message is used to invite users to a channel. The parameter <nickname> is the nickname of the person to be invited to the target channel <channel>. There is no requirement that the channel the target user is being invited to must exist or be a valid channel. To invite a user to a channel which is invite only (MODE +i), the client sending the invite must be recognised as being a channel operator on the given channel.

Numeric Replies:

ERR_NEEDMOREPARAMS	ERR_NOSUCHNICK
ERR_NOTONCHANNEL	ERR_USERONCHANNEL
ERR_CHANOPRIVSNEEDED	
RPL_INVITING	RPL_AWAY

Examples:

:Angel INVITE Wiz #Dust ; User Angel inviting WiZ to channel #Dust

INVITE Wiz #Twilight\_Zone ; Command to invite WiZ to #Twilight\_zone

#### 4.2.8 Kick command

Command: KICK

Parameters: <channel> <user> [<comment>]

The KICK command can be used to forcibly remove a user from a channel. It 'kicks them out' of the channel (forced PART).

Only a channel operator may kick another user out of a channel. Each server that receives a KICK message checks that it is valid (ie the sender is actually a channel operator) before removing the victim from the channel.

Numeric Replies:

ERR_NEEDMOREPARAMS	ERR_NOSUCHCHANNEL
ERR_BADCHANMASK	ERR_CHANOPRIVSNEEDED
ERR_NOTONCHANNEL	

Examples:

```
KICK &Melbourne Matthew      ; Kick Matthew from &Melbourne

KICK #Finnish John :Speaking English
                        ; Kick John from #Finnish using
                        "Speaking English" as the reason
                        (comment).

:WiZ KICK #Finnish John      ; KICK message from WiZ to remove John
                        from channel #Finnish
```

NOTE:

It is possible to extend the KICK command parameters to the following:

```
<channel>{,<channel>} <user>{,<user>} [<comment>]
```

#### 4.3 Server queries and commands

The server query group of commands has been designed to return information about any server which is connected to the network. All servers connected must respond to these queries and respond correctly. Any invalid response (or lack thereof) must be considered a sign of a broken server and it must be disconnected/disabled as soon as possible until the situation is remedied.

In these queries, where a parameter appears as "<server>", it will usually mean it can be a nickname or a server or a wildcard name of some sort. For each parameter, however, only one query and set of replies is to be generated.

##### 4.3.1 Version message

Command: VERSION  
Parameters: [<server>]

The VERSION message is used to query the version of the server program. An optional parameter <server> is used to query the version of the server program which a client is not directly connected to.

Numeric Replies:

ERR\_NOSUCHSERVER

RPL\_VERSION

Examples:

:Wiz VERSION \*.se ; message from Wiz to check the version  
of a server matching "\*.se"

VERSION tolsun.oulu.fi ; check the version of server  
"tolsun.oulu.fi".

#### 4.3.2 Stats message

Command: STATS

Parameters: [<query> [<server>]]

The stats message is used to query statistics of certain server. If <server> parameter is omitted, only the end of stats reply is sent back. The implementation of this command is highly dependent on the server which replies, although the server must be able to supply information as described by the queries below (or similar).

A query may be given by any single letter which is only checked by the destination server (if given as the <server> parameter) and is otherwise passed on by intermediate servers, ignored and unaltered. The following queries are those found in the current IRC implementation and provide a large portion of the setup information for that server. Although these may not be supported in the same way by other versions, all servers should be able to supply a valid reply to a STATS query which is consistent with the reply formats currently used and the purpose of the query.

The currently supported queries are:

- c - returns a list of servers which the server may connect to or allow connections from;
- h - returns a list of servers which are either forced to be treated as leaves or allowed to act as hubs;
- i - returns a list of hosts which the server allows a client to connect from;
- k - returns a list of banned username/hostname combinations for that server;
- l - returns a list of the server's connections, showing how

long each connection has been established and the traffic over that connection in bytes and messages for each direction;

- m - returns a list of commands supported by the server and the usage count for each if the usage count is non zero;
- o - returns a list of hosts from which normal clients may become operators;
- y - show Y (Class) lines from server's configuration file;
- u - returns a string showing how long the server has been up.

#### Numeric Replies:

ERR_NOSUCHSERVER	
RPL_STATSCLINE	RPL_STATSNLN
RPL_STATSILINE	RPL_STATSKLINE
RPL_STATSQLINE	RPL_STATSLLINE
RPL_STATSLINKINFO	RPL_STATSUPTIME
RPL_STATSCOMMANDS	RPL_STATSOLINE
RPL_STATSHLINE	RPL_ENDOFSTATS

#### Examples:

```
STATS m                ; check the command usage for the server
                        you are connected to

:Wiz STATS c eff.org    ; request by WiZ for C/N line
                        information from server eff.org
```

#### 4.3.3 Links message

Command: LINKS

Parameters: [[<remote server>] <server mask>]

With LINKS, a user can list all servers which are known by the server answering the query. The returned list of servers must match the mask, or if no mask is given, the full list is returned.

If <remote server> is given in addition to <server mask>, the LINKS command is forwarded to the first server found that matches that name (if any), and that server is then required to answer the query.

#### Numeric Replies:

ERR_NOSUCHSERVER	
RPL_LINKS	RPL_ENDOFLINKS

#### Examples:

LINKS \*.au ; list all servers which have a name  
that matches \*.au;

:WiZ LINKS \*.bu.edu \*.edu ; LINKS message from WiZ to the first  
server matching \*.edu for a list of  
servers matching \*.bu.edu.

#### 4.3.4 Time message

Command: TIME  
Parameters: [<server>]

The time message is used to query local time from the specified server. If the server parameter is not given, the server handling the command must reply to the query.

Numeric Replies:

ERR\_NOSUCHSERVER RPL\_TIME

Examples:

TIME tolsun.oulu.fi ; check the time on the server  
"tolson.oulu.fi"

Angel TIME \*.au ; user angel checking the time on a  
server matching "\*.au"

#### 4.3.5 Connect message

Command: CONNECT  
Parameters: <target server> [<port> [<remote server>]]

The CONNECT command can be used to force a server to try to establish a new connection to another server immediately. CONNECT is a privileged command and is to be available only to IRC Operators. If a remote server is given then the CONNECT attempt is made by that server to <target server> and <port>.

Numeric Replies:

ERR\_NOSUCHSERVER ERR\_NOPRIVILEGES  
ERR\_NEEDMOREPARAMS

Examples:

CONNECT tolsun.oulu.fi ; Attempt to connect a server to  
tolsun.oulu.fi



```
:WiZ CONNECT eff.org 6667 csd.bu.edu
; CONNECT attempt by WiZ to get servers
eff.org and csd.bu.edu connected on port
6667.
```

#### 4.3.6 Trace message

Command: TRACE  
Parameters: [<server>]

TRACE command is used to find the route to specific server. Each server that processes this message must tell the sender about it by sending a reply indicating it is a pass-through link, forming a chain of replies similar to that gained from using "traceroute". After sending this reply back, it must then send the TRACE message to the next server until given server is reached. If the <server> parameter is omitted, it is recommended that TRACE command send a message to the sender telling which servers the current server has direct connection to.

If the destination given by "<server>" is an actual server, then the destination server is required to report all servers and users which are connected to it, although only operators are permitted to see users present. If the destination given by <server> is a nickname, they only a reply for that nickname is given.

##### Numeric Replies:

ERR\_NOSUCHSERVER

If the TRACE message is destined for another server, all intermediate servers must return a RPL\_TRACELINK reply to indicate that the TRACE passed through it and where its going next.

RPL\_TRACELINK

A TRACE reply may be composed of any number of the following numeric replies.

RPL\_TRACECONNECTING  
RPL\_TRACEUNKNOWN  
RPL\_TRACEUSER  
RPL\_TRACESERVICE  
RPL\_TRACECLASS

RPL\_TRACEHANDSHAKE  
RPL\_TRACEOPERATOR  
RPL\_TRACESERVER  
RPL\_TRACENEWTYPE

##### Examples:

```
TRACE *.oulu.fi ; TRACE to a server matching *.oulu.fi
```

:WiZ TRACE AngelDust ; TRACE issued by WiZ to nick AngelDust

#### 4.3.7 Admin command

Command: ADMIN  
Parameters: [<server>]

The admin message is used to find the name of the administrator of the given server, or current server if <server> parameter is omitted. Each server must have the ability to forward ADMIN messages to other servers.

Numeric Replies:

ERR_NOSUCHSERVER	
RPL_ADMINME	RPL_ADMINLOC1
RPL_ADMINLOC2	RPL_ADMINEMAIL

Examples:

ADMIN tolsun.oulu.fi	; request an ADMIN reply from tolsun.oulu.fi
:WiZ ADMIN *.edu	; ADMIN request from WiZ for first server found to match *.edu.

#### 4.3.8 Info command

Command: INFO  
Parameters: [<server>]

The INFO command is required to return information which describes the server: its version, when it was compiled, the patchlevel, when it was started, and any other miscellaneous information which may be considered to be relevant.

Numeric Replies:

ERR_NOSUCHSERVER	
RPL_INFO	RPL_ENDOFINFO

Examples:

INFO csd.bu.edu	; request an INFO reply from csd.bu.edu
:Avalon INFO *.fi	; INFO request from Avalon for first server found to match *.fi.

INFO Angel ; request info from the server that  
Angel is connected to.

#### 4.4 Sending messages

The main purpose of the IRC protocol is to provide a base for clients to communicate with each other. PRIVMSG and NOTICE are the only messages available which actually perform delivery of a text message from one client to another - the rest just make it possible and try to ensure it happens in a reliable and structured manner.

##### 4.4.1 Private messages

Command: PRIVMSG

Parameters: <receiver>{,<receiver>} <text to be sent>

PRIVMSG is used to send private messages between users. <receiver> is the nickname of the receiver of the message. <receiver> can also be a list of names or channels separated with commas.

The <receiver> parameter may also me a host mask (#mask) or server mask (\$mask). In both cases the server will only send the PRIVMSG to those who have a server or host matching the mask. The mask must have at least 1 (one) "." in it and no wildcards following the last ".". This requirement exists to prevent people sending messages to "\*" or "\$\*", which would broadcast to all users; from experience, this is abused more than used responsibly and properly. Wildcards are the '\*' and '?' characters. This extension to the PRIVMSG command is only available to Operators.

Numeric Replies:

ERR_NORECIPIENT	ERR_NOTEXTTOSEND
ERR_CANNOTSENDTOCHAN	ERR_NOTOPLEVEL
ERR_WILDTOPLEVEL	ERR_TOOMANYTARGETS
ERR_NOSUCHNICK	
RPL_AWAY	

Examples:

```
:Angel PRIVMSG Wiz :Hello are you receiving this message ?
; Message from Angel to Wiz.
```

```
PRIVMSG Angel :yes I'm receiving it !receiving it !'u>(768u+1n) .br ;
Message to Angel.
```

```
PRIVMSG jto@tolsun.oulu.fi :Hello !
; Message to a client on server
```

tolsun.oulu.fi with username of "jto".

PRIVMSG \$.fi :Server tolsun.oulu.fi rebooting.  
; Message to everyone on a server which  
has a name matching \*.fi.

PRIVMSG #\*.edu :NSFNet is undergoing work, expect interruptions  
; Message to all users who come from a  
host which has a name matching \*.edu.

#### 4.4.2 Notice

Command: NOTICE  
Parameters: <nickname> <text>

The NOTICE message is used similarly to PRIVMSG. The difference between NOTICE and PRIVMSG is that automatic replies must never be sent in response to a NOTICE message. This rule applies to servers too - they must not send any error reply back to the client on receipt of a notice. The object of this rule is to avoid loops between a client automatically sending something in response to something it received. This is typically used by automatons (clients with either an AI or other interactive program controlling their actions) which are always seen to be replying lest they end up in a loop with another automaton.

See PRIVMSG for more details on replies and examples.

#### 4.5 User based queries

User queries are a group of commands which are primarily concerned with finding details on a particular user or group users. When using wildcards with any of these commands, if they match, they will only return information on users who are 'visible' to you. The visibility of a user is determined as a combination of the user's mode and the common set of channels you are both on.

##### 4.5.1 Who query

Command: WHO  
Parameters: [<name> [<o>]]

The WHO message is used by a client to generate a query which returns a list of information which 'matches' the <name> parameter given by the client. In the absence of the <name> parameter, all visible (users who aren't invisible (user mode +i) and who don't have a common channel with the requesting client) are listed. The same result can be achieved by using a <name> of "0" or any wildcard which

will end up matching every entry possible.

The <name> passed to WHO is matched against users' host, server, real name and nickname if the channel <name> cannot be found.

If the "o" parameter is passed only operators are returned according to the name mask supplied.

Numeric Replies:

ERR_NOSUCHSERVER	
RPL_WHOREPLY	RPL_ENDOFWHO

Examples:

WHO *.fi	; List all users who match against "*.fi".
----------	---

WHO jto* o	; List all users with a match against "jto*" if they are an operator.
------------	--

#### 4.5.2 Whois query

Command: WHOIS

Parameters: [<server>] <nickmask>[,<nickmask>[,...]]

This message is used to query information about particular user. The server will answer this message with several numeric messages indicating different statuses of each user which matches the nickmask (if you are entitled to see them). If no wildcard is present in the <nickmask>, any information about that nick which you are allowed to see is presented. A comma (',') separated list of nicknames may be given.

The latter version sends the query to a specific server. It is useful if you want to know how long the user in question has been idle as only local server (ie. the server the user is directly connected to) knows that information, while everything else is globally known.

Numeric Replies:

ERR_NOSUCHSERVER	ERR_NONICKNAMEGIVEN
RPL_WHOSUSER	RPL_WHOSCHANNELS
RPL_WHOSCHANNELS	RPL_WHOSISSERVER
RPL_AWAY	RPL_WHOSISOPERATOR
RPL_WHOSIDLE	ERR_NOSUCHNICK
RPL_ENDOFWHOS	

**Examples:**

WHOIS wiz ; return available user information  
about nick WiZ

WHOIS eff.org trillian ; ask server eff.org for user  
information about trillian

**4.5.3 Whowas**

Command: WHOWAS

Parameters: <nickname> [<count> [<server>]]

Whowas asks for information about a nickname which no longer exists. This may either be due to a nickname change or the user leaving IRC. In response to this query, the server searches through its nickname history, looking for any nicks which are lexically the same (no wild card matching here). The history is searched backward, returning the most recent entry first. If there are multiple entries, up to <count> replies will be returned (or all of them if no <count> parameter is given). If a non-positive number is passed as being <count>, then a full search is done.

**Numeric Replies:**

ERR\_NONICKNAMEGIVEN  
RPL\_WHOWASUSER  
RPL\_ENDOFWHOWAS

ERR\_WASNOSUCHNICK  
RPL\_WHOWISSERVER

**Examples:**

WHOWAS Wiz ; return all information in the nick  
history about nick "WiZ";

WHOWAS Mermaid 9 ; return at most, the 9 most recent  
entries in the nick history for  
"Mermaid";

WHOWAS Trillian 1 \*.edu ; return the most recent history for  
"Trillian" from the first server found  
to match "\*.edu".

**4.6 Miscellaneous messages**

Messages in this category do not fit into any of the above categories but are nonetheless still a part of and required by the protocol.

#### 4.6.1 Kill message

Command: KILL

Parameters: <nickname> <comment>

The KILL message is used to cause a client-server connection to be closed by the server which has the actual connection. KILL is used by servers when they encounter a duplicate entry in the list of valid nicknames and is used to remove both entries. It is also available to operators.

Clients which have automatic reconnect algorithms effectively make this command useless since the disconnection is only brief. It does however break the flow of data and can be used to stop large amounts of being abused, any user may elect to receive KILL messages generated for others to keep an 'eye' on would be trouble spots.

In an arena where nicknames are required to be globally unique at all times, KILL messages are sent whenever 'duplicates' are detected (that is an attempt to register two users with the same nickname) in the hope that both of them will disappear and only 1 reappear.

The comment given must reflect the actual reason for the KILL. For server-generated KILLs it usually is made up of details concerning the origins of the two conflicting nicknames. For users it is left up to them to provide an adequate reason to satisfy others who see it. To prevent/discourage fake KILLs from being generated to hide the identify of the KILLer, the comment also shows a 'kill-path' which is updated by each server it passes through, each prepending its name to the path.

Numeric Replies:

ERR\_NOPRIVILEGES  
ERR\_NOSUCHNICK

ERR\_NEEDMOREPARAMS  
ERR\_CANTKILLSERVER

```
KILL David (csd.bu.edu <- tolsun.oulu.fi)
                                ; Nickname collision between csd.bu.edu
                                and tolsun.oulu.fi
```

NOTE:

It is recommended that only Operators be allowed to kill other users with KILL message. In an ideal world not even operators would need to do this and it would be left to servers to deal with.

#### 4.6.2 Ping message

Command: PING

Parameters: <server1> [<server2>]

The PING message is used to test the presence of an active client at the other end of the connection. A PING message is sent at regular intervals if no other activity detected coming from a connection. If a connection fails to respond to a PING command within a set amount of time, that connection is closed.

Any client which receives a PING message must respond to <server1> (server which sent the PING message out) as quickly as possible with an appropriate PONG message to indicate it is still there and alive. Servers should not respond to PING commands but rely on PINGs from the other end of the connection to indicate the connection is alive. If the <server2> parameter is specified, the PING message gets forwarded there.

Numeric Replies:

ERR\_NOORIGIN

ERR\_NOSUCHSERVER

Examples:

PING tolsun.oulu.fi ; server sending a PING message to  
another server to indicate it is still  
alive.

PING WiZ ; PING message being sent to nick WiZ

#### 4.6.3 Pong message

Command: PONG

Parameters: <daemon> [<daemon2>]

PONG message is a reply to ping message. If parameter <daemon2> is given this message must be forwarded to given daemon. The <daemon> parameter is the name of the daemon who has responded to PING message and generated this message.

Numeric Replies:

ERR\_NOORIGIN

ERR\_NOSUCHSERVER

Examples:

PONG csd.bu.edu tolsun.oulu.fi ; PONG message from csd.bu.edu to



tolsun.oulu.fi

#### 4.6.4 Error

Command: ERROR  
Parameters: <error message>

The ERROR command is for use by servers when reporting a serious or fatal error to its operators. It may also be sent from one server to another but must not be accepted from any normal unknown clients.

An ERROR message is for use for reporting errors which occur with a server-to-server link only. An ERROR message is sent to the server at the other end (which sends it to all of its connected operators) and to all operators currently connected. It is not to be passed onto any other servers by a server if it is received from a server.

When a server sends a received ERROR message to its operators, the message should be encapsulated inside a NOTICE message, indicating that the client was not responsible for the error.

Numerics:

None.

Examples:

ERROR :Server \*.fi already exists; ERROR message to the other server  
which caused this error.

NOTICE WiZ :ERROR from csd.bu.edu -- Server \*.fi already exists  
; Same ERROR message as above but sent  
to user WiZ on the other server.

#### 5. OPTIONALS

This section describes OPTIONAL messages. They are not required in a working server implementation of the protocol described herein. In the absence of the option, an error reply message must be generated or an unknown command error. If the message is destined for another server to answer then it must be passed on (elementary parsing required) The allocated numerics for this are listed with the messages below.

##### 5.1 Away

Command: AWAY  
Parameters: [message]

With the AWAY message, clients can set an automatic reply string for any PRIVMSG commands directed at them (not to a channel they are on). The automatic reply is sent by the server to client sending the PRIVMSG command. The only replying server is the one to which the sending client is connected to.

The AWAY message is used either with one parameter (to set an AWAY message) or with no parameters (to remove the AWAY message).

Numeric Replies:

RPL\_UNAWAY

RPL\_NOWAWAY

Examples:

AWAY :Gone to lunch. Back in 5 ; set away message to "Gone to lunch.  
Back in 5".

:WiZ AWAY ; unmark WiZ as being away.

## 5.2 Rehash message

Command: REHASH  
Parameters: None

The rehash message can be used by the operator to force the server to re-read and process its configuration file.

Numeric Replies:

RPL\_REHASHING

ERR\_NOPRIVILEGES

Examples:

REHASH ; message from client with operator  
status to server asking it to reread its  
configuration file.

## 5.3 Restart message

Command: RESTART  
Parameters: None

The restart message can only be used by an operator to force a server restart itself. This message is optional since it may be viewed as a risk to allow arbitrary people to connect to a server as an operator and execute this command, causing (at least) a disruption to service.

The RESTART command must always be fully processed by the server to which the sending client is connected and not be passed onto other connected servers.

Numeric Replies:

ERR\_NOPRIVILEGES

Examples:

RESTART ; no parameters required.

#### 5.4 Summon message

Command: SUMMON

Parameters: <user> [<server>]

The SUMMON command can be used to give users who are on a host running an IRC server a message asking them to please join IRC. This message is only sent if the target server (a) has SUMMON enabled, (b) the user is logged in and (c) the server process can write to the user's tty (or similar).

If no <server> parameter is given it tries to summon <user> from the server the client is connected to is assumed as the target.

If summon is not enabled in a server, it must return the ERR\_SUMMONDISABLED numeric and pass the summon message onwards.

Numeric Replies:

ERR\_NORECIPIENT

ERR\_FILEERROR

ERR\_NOLOGIN

ERR\_NOSUCHSERVER

RPL\_SUMMONING

Examples:

SUMMON jto ; summon user jto on the server's host

SUMMON jto tolsun.oulu.fi ; summon user jto on the host which a server named "tolsun.oulu.fi" is running.

#### 5.5 Users

Command: USERS

Parameters: [<server>]

The USERS command returns a list of users logged into the server in a similar format to who(1), rusers(1) and finger(1). Some people may disable this command on their server for security related reasons. If disabled, the correct numeric must be returned to indicate this.

Numeric Replies:

ERR_NOSUCHSERVER	ERR_FILEERROR
RPL_USERSSTART	RPL_USERS
RPL_NOUSERS	RPL_ENDOFUSERS
ERR_USERSDISABLED	

Disabled Reply:

ERR\_USERSDISABLED

Examples:

USERS eff.org	; request a list of users logged in on server eff.org
:John USERS tolsun.oulu.fi	; request from John for a list of users logged in on server tolsun.oulu.fi

## 5.6 Operwall message

Command: WALLOPS

Parameters: Text to be sent to all operators currently online

Sends a message to all operators currently online. After implementing WALLOPS as a user command it was found that it was often and commonly abused as a means of sending a message to a lot of people (much similar to WALL). Due to this it is recommended that the current implementation of WALLOPS be used as an example by allowing and recognising only servers as the senders of WALLOPS.

Numeric Replies:

ERR\_NEEDMOREPARAMS

Examples:

:csd.bu.edu WALLOPS :Connect '\*.uiuc.edu 6667' from Joshua; WALLOPS message from csd.bu.edu announcing a CONNECT message it received and acted upon from Joshua.

### 5.7 Userhost message

Command: USERHOST

Parameters: <nickname>{<space><nickname>}

The USERHOST command takes a list of up to 5 nicknames, each separated by a space character and returns a list of information about each nickname that it found. The returned list has each reply separated by a space.

Numeric Replies:

RPL\_USERHOST

ERR\_NEEDMOREPARAMS

Examples:

USERHOST Wiz Michael Marty p ;USERHOST request for information on  
nicks "Wiz", "Michael", "Marty" and "p"

### 5.8 Ison message

Command: ISON

Parameters: <nickname>{<space><nickname>}

The ISON command was implemented to provide a quick and efficient means to get a response about whether a given nickname was currently on IRC. ISON only takes one (1) parameter: a space-separated list of nicks. For each nickname in the list that is present, the server adds that to its reply string. Thus the reply string may return empty (none of the given nicks are present), an exact copy of the parameter string (all of them present) or as any other subset of the set of nicks given in the parameter. The only limit on the number of nicks that may be checked is that the combined length must not be too large as to cause the server to chop it off so it fits in 512 characters.

ISON is only be processed by the server local to the client sending the command and thus not passed onto other servers for further processing.

Numeric Replies:

RPL\_ISON

ERR\_NEEDMOREPARAMS

Examples:

ISON phone trillian WiZ jarlek Avalon Angel Monstah  
; Sample ISON request for 7 nicks.

## 6. REPLIES

The following is a list of numeric replies which are generated in response to the commands given above. Each numeric is given with its number, name and reply string.

### 6.1 Error Replies.

- 401      ERR\_NOSUCHNICK  
          "<nickname> :No such nick/channel"  
  
          - Used to indicate the nickname parameter supplied to a  
            command is currently unused.
- 402      ERR\_NOSUCHSERVER  
          "<server name> :No such server"  
  
          - Used to indicate the server name given currently  
            doesn't exist.
- 403      ERR\_NOSUCHCHANNEL  
          "<channel name> :No such channel"  
  
          - Used to indicate the given channel name is invalid.
- 404      ERR\_CANNOTSENDTOCHAN  
          "<channel name> :Cannot send to channel"  
  
          - Sent to a user who is either (a) not on a channel  
            which is mode +n or (b) not a chanop (or mode +v) on  
            a channel which has mode +m set and is trying to send  
            a PRIVMSG message to that channel.
- 405      ERR\_TOOMANYCHANNELS  
          "<channel name> :You have joined too many \  
            channels"  
          - Sent to a user when they have joined the maximum  
            number of allowed channels and they try to join  
            another channel.
- 406      ERR\_WASNOSUCHNICK  
          "<nickname> :There was no such nickname"  
  
          - Returned by WHOWAS to indicate there is no history  
            information for that nickname.
- 407      ERR\_TOOMANYTARGETS  
          "<target> :Duplicate recipients. No message \  
            "

delivered"

- Returned to a client which is attempting to send a PRIVMSG/NOTICE using the user@host destination format and for a user@host which has several occurrences.

409 ERR\_NOORIGIN

" :No origin specified"

- PING or PONG message missing the originator parameter which is required since these commands must work without valid prefixes.

411 ERR\_NORECIPIENT

" :No recipient given (<command>)"

412 ERR\_NOTEXTTOSEND

" :No text to send"

413 ERR\_NOTOPLEVEL

"<mask> :No toplevel domain specified"

414 ERR\_WILDTOPLEVEL

"<mask> :Wildcard in toplevel domain"

- 412 - 414 are returned by PRIVMSG to indicate that the message wasn't delivered for some reason. ERR\_NOTOPLEVEL and ERR\_WILDTOPLEVEL are errors that are returned when an invalid use of "PRIVMSG \$<server>" or "PRIVMSG #<host>" is attempted.

421 ERR\_UNKNOWNCOMMAND

"<command> :Unknown command"

- Returned to a registered client to indicate that the command sent is unknown by the server.

422 ERR\_NOMOTD

" :MOTD File is missing"

- Server's MOTD file could not be opened by the server.

423 ERR\_NOADMININFO

"<server> :No administrative info available"

- Returned by a server in response to an ADMIN message when there is an error in finding the appropriate information.

424 ERR\_FILEERROR

" :File error doing <file op> on <file>"

- Generic error message used to report a failed file operation during the processing of a message.

431   ERR\_NONICKNAMEGIVEN  
      ":No nickname given"

- Returned when a nickname parameter expected for a command and isn't found.

432   ERR\_ERRONEUSNICKNAME  
      "<nick> :Erroneus nickname"

- Returned after receiving a NICK message which contains characters which do not fall in the defined set. See section x.x.x for details on valid nicknames.

433   ERR\_NICKNAMEINUSE  
      "<nick> :Nickname is already in use"

- Returned when a NICK message is processed that results in an attempt to change to a currently existing nickname.

436   ERR\_NICKCOLLISION  
      "<nick> :Nickname collision KILL"

- Returned by a server to a client when it detects a nickname collision (registered of a NICK that already exists by another server).

441   ERR\_USERNOTINCHANNEL  
      "<nick> <channel> :They aren't on that channel"

- Returned by the server to indicate that the target user of the command is not on the given channel.

442   ERR\_NOTONCHANNEL  
      "<channel> :You're not on that channel"

- Returned by the server whenever a client tries to perform a channel effecting command for which the client isn't a member.

443   ERR\_USERONCHANNEL  
      "<user> <channel> :is already on channel"

- Returned when a client tries to invite a user to a channel they are already on.



- 444      `ERR_NOLOGIN`  
          "`<user> :User not logged in`"
- Returned by the summon after a `SUMMON` command for a user was unable to be performed since they were not logged in.
- 445      `ERR_SUMMONDISABLED`  
          "`:SUMMON has been disabled`"
- Returned as a response to the `SUMMON` command. Must be returned by any server which does not implement it.
- 446      `ERR_USERSDISABLED`  
          "`:USERS has been disabled`"
- Returned as a response to the `USERS` command. Must be returned by any server which does not implement it.
- 451      `ERR_NOTREGISTERED`  
          "`:You have not registered`"
- Returned by the server to indicate that the client must be registered before the server will allow it to be parsed in detail.
- 461      `ERR_NEEDMOREPARAMS`  
          "`<command> :Not enough parameters`"
- Returned by the server by numerous commands to indicate to the client that it didn't supply enough parameters.
- 462      `ERR_ALREADYREGISTERED`  
          "`:You may not reregister`"
- Returned by the server to any link which tries to change part of the registered details (such as password or user details from second `USER` message).
- 463      `ERR_NOPERMFORHOST`  
          "`:Your host isn't among the privileged`"
- Returned to a client which attempts to register with a server which does not been setup to allow connections from the host the attempted connection is tried.

- 464      ERR\_PASSWDMISMATCH  
          ":Password incorrect"
- Returned to indicate a failed attempt at registering a connection for which a password was required and was either not given or incorrect.
- 465      ERR\_YOUREBANNEDCREEP  
          ":You are banned from this server"
- Returned after an attempt to connect and register yourself with a server which has been setup to explicitly deny connections to you.
- 467      ERR\_KEYSET  
          "<channel> :Channel key already set"
- 471      ERR\_CHANNELISFULL  
          "<channel> :Cannot join channel (+l)"
- 472      ERR\_UNKNOWNMODE  
          "<char> :is unknown mode char to me"
- 473      ERR\_INVITEONLYCHAN  
          "<channel> :Cannot join channel (+i)"
- 474      ERR\_BANNEDFROMCHAN  
          "<channel> :Cannot join channel (+b)"
- 475      ERR\_BADCHANNELKEY  
          "<channel> :Cannot join channel (+k)"
- 481      ERR\_NOPRIVILEGES  
          ":Permission Denied- You're not an IRC operator"
- Any command requiring operator privileges to operate must return this error to indicate the attempt was unsuccessful.
- 482      ERR\_CHANOPRIVSNEEDED  
          "<channel> :You're not channel operator"
- Any command requiring 'chanop' privileges (such as MODE messages) must return this error if the client making the attempt is not a chanop on the specified channel.
- 483      ERR\_CANTKILLSERVER  
          ":You cant kill a server!"
- Any attempts to use the KILL command on a server are to be refused and this error returned directly to the client.

- 491      ERR\_NOOPERHOST  
          ":No O-lines for your host"
- If a client sends an OPER message and the server has not been configured to allow connections from the client's host as an operator, this error must be returned.
- 501      ERR\_UMODEUNKNOWNFLAG  
          ":Unknown MODE flag"
- Returned by the server to indicate that a MODE message was sent with a nickname parameter and that the a mode flag sent was not recognized.
- 502      ERR\_USERSDONTMATCH  
          ":Cant change mode for other users"
- Error sent to any user trying to view or change the user mode for a user other than themselves.

## 6.2 Command responses.

- 300      RPL\_NONE  
          Dummy reply number. Not used.
- 302      RPL\_USERHOST  
          ":[<reply>{<space><reply>}]"
- Reply format used by USERHOST to list replies to the query list. The reply string is composed as follows:  
  
          <reply> ::= <nick>['\*'] '=' <'+'|'-><hostname>  
  
          The '\*' indicates whether the client has registered as an Operator. The '-' or '+' characters represent whether the client has set an AWAY message or not respectively.
- 303      RPL\_ISON  
          ":[<nick> {<space><nick>}]"
- Reply format used by ISON to list replies to the query list.
- 301      RPL\_AWAY  
          "<nick> :<away message>"

- 305 RPL\_UNAWAY  
":You are no longer marked as being away"
- 306 RPL\_NOWAWAY  
":You have been marked as being away"
- These replies are used with the AWAY command (if allowed). RPL\_AWAY is sent to any client sending a PRIVMSG to a client which is away. RPL\_AWAY is only sent by the server to which the client is connected. Replies RPL\_UNAWAY and RPL\_NOWAWAY are sent when the client removes and sets an AWAY message.
- 311 RPL\_WHOSUSER  
"<nick> <user> <host> \* :<real name>"
- 312 RPL\_WHOSSERVER  
"<nick> <server> :<server info>"
- 313 RPL\_WHOSOPERATOR  
"<nick> :is an IRC operator"
- 317 RPL\_WHOSIDLE  
"<nick> <integer> :seconds idle"
- 318 RPL\_ENDOFWHOS  
"<nick> :End of /WHOS list"
- 319 RPL\_WHOSCHANNELS  
"<nick> :{[@|+]<channel><space>}"
- Replies 311 - 313, 317 - 319 are all replies generated in response to a WHOS message. Given that there are enough parameters present, the answering server must either formulate a reply out of the above numerics (if the query nick is found) or return an error reply. The '\*' in RPL\_WHOSUSER is there as the literal character and not as a wild card. For each reply set, only RPL\_WHOSCHANNELS may appear more than once (for long lists of channel names). The '@' and '+' characters next to the channel name indicate whether a client is a channel operator or has been granted permission to speak on a moderated channel. The RPL\_ENDOFWHOS reply is used to mark the end of processing a WHOS message.
- 314 RPL\_WHOWASUSER  
"<nick> <user> <host> \* :<real name>"
- 369 RPL\_ENDOFHOWAS  
"<nick> :End of HOWAS"
- When replying to a HOWAS message, a server must use the replies RPL\_WHOWASUSER, RPL\_WHOSSERVER or ERR\_WASNOSUCHNICK for each nickname in the presented

list. At the end of all reply batches, there must be RPL\_ENDOFWHOWAS (even if there was only one reply and it was an error).

321 RPL\_LISTSTART  
"Channel :Users Name"

322 RPL\_LIST  
"<channel> <# visible> :<topic>"

323 RPL\_LISTEND  
":End of /LIST"

- Replies RPL\_LISTSTART, RPL\_LIST, RPL\_LISTEND mark the start, actual replies with data and end of the server's response to a LIST command. If there are no channels available to return, only the start and end reply must be sent.

324 RPL\_CHANNELMODEIS  
"<channel> <mode> <mode params>"

331 RPL\_NOTOPIC  
"<channel> :No topic is set"

332 RPL\_TOPIC  
"<channel> :<topic>"

- When sending a TOPIC message to determine the channel topic, one of two replies is sent. If the topic is set, RPL\_TOPIC is sent back else RPL\_NOTOPIC.

341 RPL\_INVITING  
"<channel> <nick>"

- Returned by the server to indicate that the attempted INVITE message was successful and is being passed onto the end client.

342 RPL\_SUMMONING  
"<user> :Summoning user to IRC"

- Returned by a server answering a SUMMON message to indicate that it is summoning that user.

351 RPL\_VERSION  
"<version>.<debuglevel> <server> :<comments>"

- Reply by the server showing its version details. The <version> is the version of the software being

used (including any patchlevel revisions) and the <debuglevel> is used to indicate if the server is running in "debug mode".

The "comments" field may contain any comments about the version or further version details.

```

352 RPL_WHOREPLY
    "<channel> <user> <host> <server> <nick> \
    <H|G>[*][@|+] :<hopcount> <real name>"
315 RPL_ENDOFWHO
    "<name> :End of /WHO list"

```

- The RPL\_WHOREPLY and RPL\_ENDOFWHO pair are used to answer a WHO message. The RPL\_WHOREPLY is only sent if there is an appropriate match to the WHO query. If there is a list of parameters supplied with a WHO message, a RPL\_ENDOFWHO must be sent after processing each list item with <name> being the item.

```

353 RPL_NAMREPLY
    "<channel> :[[@|+]<nick> [[@|+]<nick> [...]]]"
366 RPL_ENDOFNAMES
    "<channel> :End of /NAMES list"

```

- To reply to a NAMES message, a reply pair consisting of RPL\_NAMREPLY and RPL\_ENDOFNAMES is sent by the server back to the client. If there is no channel found as in the query, then only RPL\_ENDOFNAMES is returned. The exception to this is when a NAMES message is sent with no parameters and all visible channels and contents are sent back in a series of RPL\_NAMREPLY messages with a RPL\_ENDOFNAMES to mark the end.

```

364 RPL_LINKS
    "<mask> <server> :<hopcount> <server info>"
365 RPL_ENDOFLINKS
    "<mask> :End of /LINKS list"

```

- In replying to the LINKS message, a server must send replies back using the RPL\_LINKS numeric and mark the end of the list using an RPL\_ENDOFLINKS reply.

```

367 RPL_BANLIST
    "<channel> <banid>"
368 RPL_ENDOFBANLIST

```

"<channel> :End of channel ban list"

- When listing the active 'bans' for a given channel, a server is required to send the list back using the RPL\_BANLIST and RPL\_ENDOFBANLIST messages. A separate RPL\_BANLIST is sent for each active banid. After the banids have been listed (or if none present) a RPL\_ENDOFBANLIST must be sent.

371 RPL\_INFO  
":<string>"

374 RPL\_ENDOFINFO  
":End of /INFO list"

- A server responding to an INFO message is required to send all its 'info' in a series of RPL\_INFO messages with a RPL\_ENDOFINFO reply to indicate the end of the replies.

375 RPL\_MOTDSTART  
":- <server> Message of the day - "

372 RPL\_MOTD  
":- <text>"

376 RPL\_ENDOFMOTD  
":End of /MOTD command"

- When responding to the MOTD message and the MOTD file is found, the file is displayed line by line, with each line no longer than 80 characters, using RPL\_MOTD format replies. These should be surrounded by a RPL\_MOTDSTART (before the RPL\_MOTDs) and an RPL\_ENDOFMOTD (after).

381 RPL\_YOUREOPER  
":You are now an IRC operator"

- RPL\_YOUREOPER is sent back to a client which has just successfully issued an OPER message and gained operator status.

382 RPL\_REHASHING  
"<config file> :Rehashing"

- If the REHASH option is used and an operator sends a REHASH message, an RPL\_REHASHING is sent back to the operator.

391 RPL\_TIME

"<server> :<string showing server's local time>"

- When replying to the TIME message, a server must send the reply using the RPL\_TIME format above. The string showing the time need only contain the correct day and time there. There is no further requirement for the time string.

392 RPL\_USERSSTART  
":UserID Terminal Host"

393 RPL\_USERS  
":%-8s %-9s %-8s"

394 RPL\_ENDOFUSERS  
":End of users"

395 RPL\_NOUSERS  
":Nobody logged in"

- If the USERS message is handled by a server, the replies RPL\_USERSTART, RPL\_USERS, RPL\_ENDOFUSERS and RPL\_NOUSERS are used. RPL\_USERSSTART must be sent first, following by either a sequence of RPL\_USERS or a single RPL\_NOUSER. Following this is RPL\_ENDOFUSERS.

200 RPL\_TRACELINK  
"Link <version & debug level> <destination> \  
<next server>"

201 RPL\_TRACECONNECTING  
"Try. <class> <server>"

202 RPL\_TRACEHANDSHAKE  
"H.S. <class> <server>"

203 RPL\_TRACEUNKNOWN  
"???? <class> [<client IP address in dot form>]"

204 RPL\_TRACEOPERATOR  
"Oper <class> <nick>"

205 RPL\_TRACEUSER  
"User <class> <nick>"

206 RPL\_TRACESERVER  
"Serv <class> <int>S <int>C <server> \  
<nick!user|\*!\*>@<host|server>"

208 RPL\_TRACENEWTYPE  
"<newtype> 0 <client name>"

261 RPL\_TRACELOG  
"File <logfile> <debug level>"

- The RPL\_TRACE\* are all returned by the server in response to the TRACE message. How many are returned is dependent on the the TRACE message and



whether it was sent by an operator or not. There is no predefined order for which occurs first. Replies RPL\_TRACEUNKNOWN, RPL\_TRACECONNECTING and RPL\_TRACEHANDSHAKE are all used for connections which have not been fully established and are either unknown, still attempting to connect or in the process of completing the 'server handshake'. RPL\_TRACELINK is sent by any server which handles a TRACE message and has to pass it on to another server. The list of RPL\_TRACELINKs sent in response to a TRACE command traversing the IRC network should reflect the actual connectivity of the servers themselves along that path. RPL\_TRACENEWTYPE is to be used for any connection which does not fit in the other categories but is being displayed anyway.

```

211 RPL_STATSLINKINFO
    "<linkname> <sendq> <sent messages> \
    <sent bytes> <received messages> \
    <received bytes> <time open>"
212 RPL_STATSCOMMANDS
    "<command> <count>"
213 RPL_STATSCLINE
    "C <host> * <name> <port> <class>"
214 RPL_STATSNLIN
    "N <host> * <name> <port> <class>"
215 RPL_STATSILIN
    "I <host> * <host> <port> <class>"
216 RPL_STATSKLIN
    "K <host> * <username> <port> <class>"
218 RPL_STATSYLIN
    "Y <class> <ping frequency> <connect \
    frequency> <max sendq>"
219 RPL_ENDOFSTATS
    "<stats letter> :End of /STATS report"
241 RPL_STATSLLINE
    "L <hostmask> * <servername> <maxdepth>"
242 RPL_STATSUPTIME
    ":Server Up %d days %d:%02d:%02d"
243 RPL_STATSOLIN
    "O <hostmask> * <name>"
244 RPL_STATSHLIN
    "H <hostmask> * <servername>"

221 RPL_UMODEIS
    "<user mode string>"

```

- To answer a query about a client's own mode, RPL\_UMODEIS is sent back.

```
251 RPL_USERCLIENT
    ":There are <integer> users and <integer> \
    invisible on <integer> servers"
252 RPL_USEROP
    "<integer> :operator(s) online"
253 RPL_USERUNKNOWN
    "<integer> :unknown connection(s)"
254 RPL_USERCHANNELS
    "<integer> :channels formed"
255 RPL_USERME
    ":I have <integer> clients and <integer> \
    servers"
```

- In processing an LUSERS message, the server sends a set of replies from RPL\_USERCLIENT, RPL\_USEROP, RPL\_USERUNKNOWN, RPL\_USERCHANNELS and RPL\_USERME. When replying, a server must send back RPL\_USERCLIENT and RPL\_USERME. The other replies are only sent back if a non-zero count is found for them.

```
256 RPL_ADMINME
    "<server> :Administrative info"
257 RPL_ADMINLOC1
    ":<admin info>"
258 RPL_ADMINLOC2
    ":<admin info>"
259 RPL_ADMINEMAIL
    ":<admin info>"
```

- When replying to an ADMIN message, a server is expected to use replies RPL\_ADMINME through to RPL\_ADMINEMAIL and provide a text message with each. For RPL\_ADMINLOC1 a description of what city, state and country the server is in is expected, followed by details of the university and department (RPL\_ADMINLOC2) and finally the administrative contact for the server (an email address here is required) in RPL\_ADMINEMAIL.

### 6.3 Reserved numerics.

These numerics are not described above since they fall into one of the following categories:

1. no longer in use;
2. reserved for future planned use;
3. in current use but are part of a non-generic 'feature' of the current IRC server.

209	RPL_TRACECLASS	217	RPL_STATSQLINE
231	RPL_SERVICEINFO	232	RPL_ENDOFSERVICES
233	RPL_SERVICE	234	RPL_SERVLIST
235	RPL_SERVLISTEND		
316	RPL_WHOSCHANOP	361	RPL_KILLDONE
362	RPL_CLOSING	363	RPL_CLOSEEND
373	RPL_INFOSTART	384	RPL_MYPORTIS
466	ERR_YOULLBEBANNED	476	ERR_BADCHANMASK
492	ERR_NOSERVICEHOST		

### 7. Client and server authentication

Clients and servers are both subject to the same level of authentication. For both, an IP number to hostname lookup (and reverse check on this) is performed for all connections made to the server. Both connections are then subject to a password check (if there is a password set for that connection). These checks are possible on all connections although the password check is only commonly used with servers.

An additional check that is becoming of more and more common is that of the username responsible for making the connection. Finding the username of the other end of the connection typically involves connecting to an authentication server such as IDENT as described in RFC 1413.

Given that without passwords it is not easy to reliably determine who is on the other end of a network connection, use of passwords is strongly recommended on inter-server connections in addition to any other measures such as using an ident server.

### 8. Current implementations

The only current implementation of this protocol is the IRC server, version 2.8. Earlier versions may implement some or all of the commands described by this document with NOTICE messages replacing

many of the numeric replies. Unfortunately, due to backward compatibility requirements, the implementation of some parts of this document varies with what is laid out. On notable difference is:

- \* recognition that any LF or CR anywhere in a message marks the end of that message (instead of requiring CR-LF);

The rest of this section deals with issues that are mostly of importance to those who wish to implement a server but some parts also apply directly to clients as well.

## 8.1 Network protocol: TCP - why it is best used here.

IRC has been implemented on top of TCP since TCP supplies a reliable network protocol which is well suited to this scale of conferencing. The use of multicast IP is an alternative, but it is not widely available or supported at the present time.

### 8.1.1 Support of Unix sockets

Given that Unix domain sockets allow listen/connect operations, the current implementation can be configured to listen and accept both client and server connections on a Unix domain socket. These are recognized as sockets where the hostname starts with a '/'.

When providing any information about the connections on a Unix domain socket, the server is required to supplant the actual hostname in place of the pathname unless the actual socket name is being asked for.

## 8.2 Command Parsing

To provide useful 'non-buffered' network IO for clients and servers, each connection is given its own private 'input buffer' in which the results of the most recent read and parsing are kept. A buffer size of 512 bytes is used so as to hold 1 full message, although, this will usually hold several commands. The private buffer is parsed after every read operation for valid messages. When dealing with multiple messages from one client in the buffer, care should be taken in case one happens to cause the client to be 'removed'.

## 8.3 Message delivery

It is common to find network links saturated or hosts to which you are sending data unable to send data. Although Unix typically handles this through the TCP window and internal buffers, the server often has large amounts of data to send (especially when a new server-server link forms) and the small buffers provided in the

kernel are not enough for the outgoing queue. To alleviate this problem, a "send queue" is used as a FIFO queue for data to be sent. A typical "send queue" may grow to 200 Kbytes on a large IRC network with a slow network connection when a new server connects.

When polling its connections, a server will first read and parse all incoming data, queuing any data to be sent out. When all available input is processed, the queued data is sent. This reduces the number of write() system calls and helps TCP make bigger packets.

#### 8.4 Connection 'Liveness'

To detect when a connection has died or become unresponsive, the server must ping each of its connections that it doesn't get a response from in a given amount of time.

If a connection doesn't respond in time, its connection is closed using the appropriate procedures. A connection is also dropped if its sendq grows beyond the maximum allowed, because it is better to close a slow connection than have a server process block.

#### 8.5 Establishing a server to client connection

Upon connecting to an IRC server, a client is sent the MOTD (if present) as well as the current user/server count (as per the LUSER command). The server is also required to give an unambiguous message to the client which states its name and version as well as any other introductory messages which may be deemed appropriate.

After dealing with this, the server must then send out the new user's nickname and other information as supplied by itself (USER command) and as the server could discover (from DNS/authentication servers). The server must send this information out with NICK first followed by USER.

#### 8.6 Establishing a server-server connection.

The process of establishing of a server-to-server connection is fraught with danger since there are many possible areas where problems can occur - the least of which are race conditions.

After a server has received a connection following by a PASS/SERVER pair which were recognised as being valid, the server should then reply with its own PASS/SERVER information for that connection as well as all of the other state information it knows about as described below.

When the initiating server receives a PASS/SERVER pair, it too then

checks that the server responding is authenticated properly before accepting the connection to be that server.

#### 8.6.1 Server exchange of state information when connecting

The order of state information being exchanged between servers is essential. The required order is as follows:

- \* all known other servers;
- \* all known user information;
- \* all known channel information.

Information regarding servers is sent via extra SERVER messages, user information with NICK/USER/MODE/JOIN messages and channels with MODE messages.

NOTE: channel topics are *\*NOT\** exchanged here because the TOPIC command overwrites any old topic information, so at best, the two sides of the connection would exchange topics.

By passing the state information about servers first, any collisions with servers that already exist occur before nickname collisions due to a second server introducing a particular nickname. Due to the IRC network only being able to exist as an acyclic graph, it may be possible that the network has already reconnected in another location, the place where the collision occurs indicating where the net needs to split.

#### 8.7 Terminating server-client connections

When a client connection closes, a QUIT message is generated on behalf of the client by the server to which the client connected. No other message is to be generated or used.

#### 8.8 Terminating server-server connections

If a server-server connection is closed, either via a remotely generated SQUIT or 'natural' causes, the rest of the connected IRC network must have its information updated with by the server which detected the closure. The server then sends a list of SQUITs (one for each server behind that connection) and a list of QUITs (again, one for each client behind that connection).

### 8.9 Tracking nickname changes

All IRC servers are required to keep a history of recent nickname changes. This is required to allow the server to have a chance of keeping in touch of things when nick-change race conditions occur with commands which manipulate them. Commands which must trace nick changes are:

- \* KILL (the nick being killed)
- \* MODE (+/- o,v)
- \* KICK (the nick being kicked)

No other commands are to have nick changes checked for.

In the above cases, the server is required to first check for the existence of the nickname, then check its history to see who that nick currently belongs to (if anyone!). This reduces the chances of race conditions but they can still occur with the server ending up affecting the wrong client. When performing a change trace for an above command it is recommended that a time range be given and entries which are too old ignored.

For a reasonable history, a server should be able to keep previous nickname for every client it knows about if they all decided to change. This size is limited by other factors (such as memory, etc).

### 8.10 Flood control of clients

With a large network of interconnected IRC servers, it is quite easy for any single client attached to the network to supply a continuous stream of messages that result in not only flooding the network, but also degrading the level of service provided to others. Rather than require every 'victim' to be provide their own protection, flood protection was written into the server and is applied to all clients except services. The current algorithm is as follows:

- \* check to see if client's 'message timer' is less than current time (set to be equal if it is);
- \* read any data present from the client;
- \* while the timer is less than ten seconds ahead of the current time, parse any present messages and penalize the client by 2 seconds for each message;

which in essence means that the client may send 1 message every 2

seconds without being adversely affected.

### 8.11 Non-blocking lookups

In a real-time environment, it is essential that a server process do as little waiting as possible so that all the clients are serviced fairly. Obviously this requires non-blocking IO on all network read/write operations. For normal server connections, this was not difficult, but there are other support operations that may cause the server to block (such as disk reads). Where possible, such activity should be performed with a short timeout.

#### 8.11.1 Hostname (DNS) lookups

Using the standard resolver libraries from Berkeley and others has meant large delays in some cases where replies have timed out. To avoid this, a separate set of DNS routines were written which were setup for non-blocking IO operations and then polled from within the main server IO loop.

#### 8.11.2 Username (Ident) lookups

Although there are numerous ident libraries for use and inclusion into other programs, these caused problems since they operated in a synchronous manner and resulted in frequent delays. Again the solution was to write a set of routines which would cooperate with the rest of the server and work using non-blocking IO.

### 8.12 Configuration File

To provide a flexible way of setting up and running the server, it is recommended that a configuration file be used which contains instructions to the server on the following:

- \* which hosts to accept client connections from;
- \* which hosts to allow to connect as servers;
- \* which hosts to connect to (both actively and passively);
- \* information about where the server is (university, city/state, company are examples of this);
- \* who is responsible for the server and an email address at which they can be contacted;
- \* hostnames and passwords for clients which wish to be given



access to restricted operator commands.

In specifying hostnames, both domain names and use of the 'dot' notation (127.0.0.1) should both be accepted. It must be possible to specify the password to be used/accepted for all outgoing and incoming connections (although the only outgoing connections are those to other servers).

The above list is the minimum requirement for any server which wishes to make a connection with another server. Other items which may be of use are:

- \* specifying which servers other server may introduce;
- \* how deep a server branch is allowed to become;
- \* hours during which clients may connect.

#### 8.12.1 Allowing clients to connect

A server should use some sort of 'access control list' (either in the configuration file or elsewhere) that is read at startup and used to decide what hosts clients may use to connect to it.

Both 'deny' and 'allow' should be implemented to provide the required flexibility for host access control.

#### 8.12.2 Operators

The granting of operator privileges to a disruptive person can have dire consequences for the well-being of the IRC net in general due to the powers given to them. Thus, the acquisition of such powers should not be very easy. The current setup requires two 'passwords' to be used although one of them is usually easy guessed. Storage of oper passwords in configuration files is preferable to hard coding them in and should be stored in a crypted format (ie using crypt(3) from Unix) to prevent easy theft.

#### 8.12.3 Allowing servers to connect

The interconnection of server is not a trivial matter: a bad connection can have a large impact on the usefulness of IRC. Thus, each server should have a list of servers to which it may connect and which servers may connect to it. Under no circumstances should a server allow an arbitrary host to connect as a server. In addition to which servers may and may not connect, the configuration file should also store the password and other characteristics of that link.

#### 8.12.4 Administrivia

To provide accurate and valid replies to the ADMIN command (see section 4.3.7), the server should find the relevant details in the configuration.

#### 8.13 Channel membership

The current server allows any registered local user to join upto 10 different channels. There is no limit imposed on non-local users so that the server remains (reasonably) consistant with all others on a channel membership basis

### 9. Current problems

There are a number of recognized problems with this protocol, all of which hope to be solved sometime in the near future during its rewrite. Currently, work is underway to find working solutions to these problems.

#### 9.1 Scalability

It is widely recognized that this protocol does not scale sufficiently well when used in a large arena. The main problem comes from the requirement that all servers know about all other servers and users and that information regarding them be updated as soon as it changes. It is also desirable to keep the number of servers low so that the path length between any two points is kept minimal and the spanning tree as strongly branched as possible.

#### 9.2 Labels

The current IRC protocol has 3 types of labels: the nickname, the channel name and the server name. Each of the three types has its own domain and no duplicates are allowed inside that domain. Currently, it is possible for users to pick the label for any of the three, resulting in collisions. It is widely recognized that this needs reworking, with a plan for unique names for channels and nicks that don't collide being desirable as well as a solution allowing a cyclic tree.

##### 9.2.1 Nicknames

The idea of the nickname on IRC is very convenient for users to use when talking to each other outside of a channel, but there is only a finite nickname space and being what they are, its not uncommon for several people to want to use the same nick. If a nickname is chosen by two people using this protocol, either one will not succeed or

both will removed by use of KILL (4.6.1).

### 9.2.2 Channels

The current channel layout requires that all servers know about all channels, their inhabitants and properties. Besides not scaling well, the issue of privacy is also a concern. A collision of channels is treated as an inclusive event (both people who create the new channel are considered to be members of it) rather than an exclusive one such as used to solve nickname collisions.

### 9.2.3 Servers

Although the number of servers is usually small relative to the number of users and channels, they two currently required to be known globally, either each one separately or hidden behind a mask.

### 9.3 Algorithms

In some places within the server code, it has not been possible to avoid  $N^2$  algorithms such as checking the channel list of a set of clients.

In current server versions, there are no database consistency checks, each server assumes that a neighbouring server is correct. This opens the door to large problems if a connecting server is buggy or otherwise tries to introduce contradictions to the existing net.

Currently, because of the lack of unique internal and global labels, there are a multitude of race conditions that exist. These race conditions generally arise from the problem of it taking time for messages to traverse and effect the IRC network. Even by changing to unique labels, there are problems with channel-related commands being disrupted.

## 10. Current support and availability

Mailing lists for IRC related discussion:

Future protocol: [ircd-three-request@eff.org](mailto:ircd-three-request@eff.org)

General discussion: [operlist-request@eff.org](mailto:operlist-request@eff.org)

Software implemenations

[cs.bu.edu/irc](http://cs.bu.edu/irc)

[nic.funet.fi:/pub/irc](http://nic.funet.fi/pub/irc)

[coombs.anu.edu.au:/pub/irc](http://coombs.anu.edu.au/pub/irc)

Newsgroup: [alt.irc](http://alt.irc)

## Security Considerations

Security issues are discussed in sections 4.1, 4.1.1, 4.1.3, 5.5, and 7.

## 12. Authors' Addresses

Jarkko Oikarinen  
Tuirantie 17 as 9  
90500 OULU  
FINLAND

Email: jto@tolsun.oulu.fi

Darren Reed  
4 Pateman Street  
Watsonia, Victoria 3087  
Australia

Email: avalon@coombs.anu.edu.au